
Thunderbolt Driver Install/Update Guide



Get the latest Thunderbolt driver from MSI website
Search for product page and click "Download" > the Thunderbolt driver update
package is under the Driver tab.



- 2. Open the Device Manager, and make sure that a Thunderbolt Contorller device is shown under "System devices" (e.g. Thunderbolt Controller 15D9).
 - ➤ If the thunderbolt controller device doesn't show in the device manager, reboot the system and press "delete" button to enter BIOS menu > Advanced > Thuderbolt firmware update, change the setting to "Enabled" and press "F10" to save configuration and reset the system.
- 3. Extract the file installer package and open the folder.
- 4. Install the driver.

If the download file contains two folders named "ThunderboltUwdSetup/ThunderboltDchSetup" and "ThunderboltApplicationLauncherSetup"

- Proceed to the steps on Page 2

If the download file only contains one folder named "ThunderboltUwdSetup"


- Proceed to the steps on Page 3

Thunderbolt Driver Install/Update Guide




If the extracted file contains the following two folders

- ThunderboltUwdSetup or ThunderboltDchSetup
- ThunderboltApplicationLauncherSetup
- A. Find and Select the Thunderbolt Driver installer folder "ThunderboltUwdSetup" or "ThunderboltDchSetup".
- B. Right click on "TbtHostController.inf" and click "Install".



C. Click "OK" to close the window after the installation complete.




- D. After installing the Thunderbolt Driver, enter another application launcher (ThunderboltApplicationLauncherSetup) folder.
- E. Right click on "TbtHostControllerExtension.inf" and click "install".
- F. After the files are installed, the driver installation process is complete.
- G. Click here to download "Thunderbolt Control Center" in Microsoft Store.

Thunderbolt Driver Install/Update Guide



If the extracted file only contains the following folder

- ThunderboltUwdSetup
- A. In the "ThunderboltUwdSetup" folder, right click on "TbtHostController.inf" and click "Install".



B. Click "OK" to close the window after the installation complete.

